


# information about exit (XI - InformationEXITDE)

The message is used by the forwarder to qualify the presentation of goods from an export transaction at the customs office of exit.

The forwarder transmits information on the intended means of transport and the place of presentation of the individual goods items; the level of detail of this information depends on the local conditions at the customs office of exit. In addition, the forwarder transmits, at his own discretion, the registration numbers of a third-party system that he uses. After permission to exit has been granted, but before the actual, physical exit of the goods from the territory of the Community, the message can also serve the forwarder to subsequently change the place of presentation of the goods. Such a transfer is only possible within the area of responsibility of a customs office of exit.

Please note the ATLAS specification that only one of the qualifications described in field XI1030/InformationType can be transmitted at a time. If, for example, a qualification for the entire process (LV) is transferred to ZODIAK via the BOX, this must first have been transmitted to ATLAS before different information for individual goods positions (LW) or packages (LP) on the means of transport (time, license plate number, loading location, …) can be transferred to ZODIAK via the BOX. However, you have the option of withdrawing the qualification currently available in ZODIAK (not yet sent to ATLAS) by additionally specifying the object action (OB0050/ObjektAktion) "RESTORE" in order to then start a new qualification.

Qualifications always refer to a presentation at the exit. The reference number from the presentation at the exit (OB0020/ObjektName from the message XP) should therefore be given as the reference number for the qualifications (OB0020/ObjektName). Qualifications are changes in presentation at the exit. "CHANGE" must therefore always be used as the object action (OB0050/ObjektAktion), even when a qualification is first transmitted.

The transmission of "Transport Equipment (XI1320 to XI1330, TransportEquipment)" (seals and possibly new container numbers) only makes sense in XI messages in which the closing identifier (XI1040/Finalization) is sent with "1" and which are sent before permission to exit is granted for the first time. However, it is possible - even if not useful - to transmit "Transport Equipment” in each XI message before permission to exit is granted for the first time. It should be noted here that the Transport Equipment must then always be reported in total, since each XI message completely replaces the group Transport Equipment. Once permission to exit (in the case of transfers) has been issued for the first time, Transport Equipment may no longer be transmitted.

This message can also only be used to communicate the completion of the exit by selecting the value "NV: No information" as the "Type of information" (XI1030/InformationType). This does not apply to forwarding at the exit. The closing identifier (XI1040/Finalization) must not be specified for "NV" as it is set automatically in ZODIAK.

All information in this document is purely informative and does not constitute instructions or templates for submitting customs declarations.
The declarant is solely responsible for the content of a customs declaration. All information is provided without warranty.