

Unloading Commentary (UR, EntladekommentarNCTSDE)

The following information is in no way an aid to submitting a specific unloading comment! All notes in this document are purely informative and should serve as an aid to the implementation of the unloading comment. Only the declarant determines which fields and which values are to be specified in an unloading comment! If the specifications of the declarant do not match the regulations presented below, you may not implement the unloading comment based on the information in this document. This applies accordingly to the information in the interface documentation for the unloading comment (Flat: UR, XML: EntladekommentarNCTSDE).
The submission of an unloading comment is subject to numerous regulations. You may only implement the unloading comment if you are aware of the regulations. The declarant is responsible for compliance with the regulations. This document only shows you the technical options for submitting an unloading comment. This document in no way replaces the regulations to be observed!
In the case of obvious seals violations or other irregularities, automatic processing and unloading is not permitted. The responsible customs office is to be informed of the seal violations and/or irregularities using the usual means of office communication and decides on how to proceed.

The "unloading comment" is the response of the authorized consignee (ZE/ZT) to the "unloading authorisation" by which the consignee notifies that the unloading has been carried out. It contains the specifications of the procedure actually established by the authorized consignee (ZE/ZT). The message is sent by the participant to the actual customs office of destination. The information transmitted with this message is important for the temporary custody following the completion of the transit procedure.

The scope of the data to be transmitted in the unloading comment depends on several factors, which are explained below in the form of examples.

The transmission of the status of a repeatable data group was previously only necessary for goods items in the data field 'Status Goods Item' (UR3005, StatusPosition). This status indicates whether the data group is unchanged ('OK'), changed ('DIFF'), new ('NEW') or to be removed ('MISS'). The new requirements for ATLAS communication make it necessary that every repeatable data group except for the seal data must be sent to the BOX with such a status. In addition, the specification of a sequence number is required, and this sequence number must match the sequence number of the corresponding data group in the Unloading Permit (UP) message.

If the instance of a repeatable data group is to be transmitted, each instance must always be specified with an ascending sequence number.

As a rule, in an unloading comment you should please transmit:

- Field "Object Name" (OB0020, ObjektName) with the reference number of the NCTS entry notification,
- Field "Object action" (OB0050, ObjektAktion) with CHANGE, additionally SEND if you would like,
- Field "Person Responsible " (OB0060, Bearbeiter) with the name of the person responsible.

All information in this document is purely informative and does not constitute instructions or templates for submitting customs declarations.
The declarant is solely responsible for the content of a customs declaration. All information is provided without warranty.

- Field "Indicator Conform" (UR1020, Conform) with "0" or "1" according to "Comment according to ATLAS" and
- Field "State of Seals OK" (UR1030, StateOfSeals) with "0" or "1" according to "Comment according to ATLAS".

Furthermore, you can generally transmit:

- A specification of the "Consignee" (UR0049 - UR0060, TraderAtDestination),
- Field "Other Things to Report" (UR1034, OtherThingsToReport)
- All repetitions of the data group "Departure Transport Means (UR1041 - UR1050, Sequence DepartureTransportMeans)" at header level,
- Field "Gross Mass" (UR2000, GrossMass),
- All repetitions of the data group "Transport Equipment" (UR2025 - UR2046, Sequence TransportEquipment) including all repetitions of the data group "Goods Item Reference" (UR2042 - UR2046, Sequence GoodsReferences), if no seals were specified in the Unloading Permit (UP) message and
- After the end of the #TRANSITIONALPERIOD, all repetitions of the data group "HouseConsignment" (UR4000 - UR4040, Sequence HouseConsignment) with "Sequence Number" (UR4000, SequenceNumber) and "Status of HouseConsignment" (UR4005, Status), to indicate in each case all repetitions of the data group "[HouseConsignment] Departure Transport Means" (UR4020 - UR4040, Sequence HouseConsignment DepartureTransportMeans), if one of the means of transport of this HouseConsignment has changed.
  Note: If "Conform Indicator" = "0 or N", all HouseConsignments must be transmitted.

Example 1: Submission of an unloading comment without unloading remark ("Indicator Conform" = "1 or J", Yes) and if the state of seals is in order ("State of the Seals Okay" = "1 or J", Yes).
In this case, you are not allowed to transmit any other fields of the unloading comment. Specifications of the HouseConsignments and Goods Items are also not allowed.

Example 2: if the state of seals is not in order ("State of Seals Okay" = "0 or N")
Then be sure to also report:

- All repetitions of the data group "Transport Equipment" (UR2025 - UR2046, Sequence TransportEquipment) with all undamaged "Seal Identifiers" (UR2040, Seal), the field "Number of Seals" (UR2030, NumberOfSeals) and all repetitions of the data group "Goods Item Reference" (UR2042 - UR2046, Sequence GoodsReferences)

and optionally:

- Field "Unloading Remark" (UR1032, UnloadingRemark) wherein you may explain the discrepancy

Example 3: if unloading remarks are present ("Conform Indicator" = "0 or N").
Then report optionally:

- Field "Unloading Remark" field (UR1032, UnloadingRemark)

and then it is essential to also report:

- Field "Gross Mass" (UR2000, GrossMass)
- All repetitions of the data group "HouseConsignment" (UR4000 - UR4040, Sequence HouseConsignment) with "Sequence Number" (UR4000, SequenceNumber) and "Status of HouseConsignment" (UR4005, Status). For "Status" NEW the field "Gross Mass" (UR4010, GrossMass) must be specified and for "Status" DIFF the specification of the Gross Mass field is optional.
- All repetitions of the data group "Goods Item" (UR3000 - UR3100, sequence ConsignmentItem) for each HouseConsignment if at least one goods item of this HouseConsignment has a "Status Goods Item" (UR3005, Status) other than OK. If the HouseConsignment has the "Status" OK or MISS, no goods items of this HouseConsignment are reported.

All information in this document is purely informative and does not constitute instructions or templates for submitting customs declarations.
The declarant is solely responsible for the content of a customs declaration. All information is provided without warranty.

If goods items are reported, then:

- All goods items with "Status Goods Item" (UR3005, Status) equal to OK or MISS are reported only with "Goods Item Number" (UR3000, GoodsItemNumber) and "Status Goods Item".
- All goods items with "Status Goods Item" (UR3005, Status) equal to NEW are transferred with the next free "Goods Item Number" and all required specifications at goods item level.
- All goods items with "Status Goods Item" (UR3005, Status) equal to DIFF must contain at least one changed field or one changed specification to "Packages" (UR3072 - UR3100, Sequence Packaging). Fields not specified will not be overwritten.

If packages are reported, the following applies:

- All packages with "Status" (UR3075, Status) equal to OK or MISS are reported with "Sequence Number" (UR3072, SequenceNumber) and "Status" only.
- All packages with "Status" (UR3075, Status) equal to NEW are transmitted with the next free "Sequence Number" and all required package level specifications.
- All packages with "Status" (UR3075, Status) equal to DIFF must contain at least one changed field. Fields not specified will not be overwritten.

All information in this document is purely informative and does not constitute instructions or templates for submitting customs declarations.
The declarant is solely responsible for the content of a customs declaration. All information is provided without warranty.